



Cisco Unified Workforce Optimization

Quality Management Recording Controls User Guide Version 11.5

First Published: First Published: July 28, 2016

Last Updated: Last Updated: July 28, 2016

THE SPECIFICATIONS AND INFORMATION REGARDING THE PRODUCTS IN THIS MANUAL ARE SUBJECT TO CHANGE WITHOUT NOTICE. ALL STATEMENTS, INFORMATION, AND RECOMMENDATIONS IN THIS MANUAL ARE BELIEVED TO BE ACCURATE BUT ARE PRESENTED WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED. USERS MUST TAKE FULL RESPONSIBILITY FOR THEIR APPLICATION OF ANY PRODUCTS.

THE SOFTWARE LICENSE AND LIMITED WARRANTY FOR THE ACCOMPANYING PRODUCT ARE SET FORTH IN THE INFORMATION PACKET THAT SHIPPED WITH THE PRODUCT AND ARE INCORPORATED HEREIN BY THIS REFERENCE. IF YOU ARE UNABLE TO LOCATE THE SOFTWARE LICENSE OR LIMITED WARRANTY, CONTACT YOUR CISCO REPRESENTATIVE FOR A COPY.

The Cisco implementation of TCP header compression is an adaptation of a program developed by the University of California, Berkeley (UCB) as part of UCB's public domain version of the UNIX operating system. All rights reserved. Copyright © 1981, Regents of the University of California.

NOTWITHSTANDING ANY OTHER WARRANTY HEREIN, ALL DOCUMENT FILES AND SOFTWARE OF THESE SUPPLIERS ARE PROVIDED "AS IS" WITH ALL FAULTS. CISCO AND THE ABOVE-NAMED SUPPLIERS DISCLAIM ALL WARRANTIES, EXPRESSED OR IMPLIED, INCLUDING, WITHOUT LIMITATION, THOSE OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT OR ARISING FROM A COURSE OF DEALING, USAGE, OR TRADE PRACTICE. IN NO EVENT SHALL CISCO OR ITS SUPPLIERS BE LIABLE FOR ANY INDIRECT, SPECIAL, CONSEQUENTIAL, OR INCIDENTAL DAMAGES, INCLUDING, WITHOUT LIMITATION, LOST PROFITS OR LOSS OR DAMAGE TO DATA ARISING OUT OF THE USE OR INABILITY TO USE THIS MANUAL, EVEN IF CISCO OR ITS SUPPLIERS HAVE BEEN ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

Any Internet Protocol (IP) addresses and phone numbers used in this document are not intended to be actual addresses and phone numbers. Any examples, command display output, network topology diagrams, and other figures included in the document are shown for illustrative purposes only. Any use of actual IP addresses or phone numbers in illustrative content is unintentional and coincidental.

Cisco and the Cisco logo are trademarks or registered trademarks of Cisco and/or its affiliates in the U.S. and other countries. To view a list of Cisco trademarks, go to this URL: www.cisco.com/go/trademarks. Third-party trademarks mentioned are the property of their respective owners. The use of the word partner does not imply a partnership relationship between Cisco and any other company. (1110R)

Quality Management Recording Controls User Guide

© 2016 Cisco Systems, Inc. All rights reserved.

Contents

Recording Controls	5
Recording Controls IP Phone Service	6
Accessing the Recording Controls IP Phone Service	6
Recording Controls Commands for the IP Phone Service	7
Recording Controls Browser Application	10
Recording Commands	12
Command Functions	12
Record Command	12
Pause Command	13
Resume Command	14
Delete Command	14
Login Command	15
Logout Command	15
Metadata Command	15
Start Segment Command	16
Stop Segment Command	17
Start Screen Command	17
Stop Screen Command	18
Config Command	18
Effect of Issuing Recording Control Commands	19
Active and Last Call	20
Using Commands with an Outbound Dialer	21

Recording Controls

Recording Controls allows you to record, store, score, and review agent calls in a contact center.

Note: Recording Controls is a separate application that is not included in Unified Workforce Optimization®.

Because there are always special cases that you cannot anticipate or handle by creating a simple quality management workflow, Recording Controls provides commands that you can use to override the business logic found in the quality management workflows. Recording Controls allows you to control which recorded calls are stored, the content of the recorded calls, and even the data associated with the calls. This is sometimes called “record on demand”, but Recording Controls allows you to do more than force the recording and storage of a call. Recording Controls allows you to:

- Tag an active call or the most recent call recording
- Record calls
- Pause and resume the recording of audio
- Start the recording of a call
- Discard previously recorded audio and screen for a call
- Delete the recording for the active call—once a call is over you cannot delete the recording
- Login or logout for hot desk recording
- Add metadata to an active call or the most recent call
- Start or stop the audio and screen recording of an active call
- Start or stop the screen recording

Recording Controls includes the following user applications:

- Recording Controls IP Phone service

Note: This feature is only available on Cisco IP phones.

- Recording Controls Browser application

Recording Controls supports the following recording types:

- Desktop Recording
- Network Recording
- Server Recording (SPAN)
- Cisco CUBE Recording via SIP
- Cisco MediaSense Recording

Note: The following recording commands are supported with Gateway/MediaSense Recording: Record Tag, Pause, Resume, Delete, and Metadata.

Note: For Gateway/MediaSense Recording, the use of recording commands is not supported for extensions in the exclusion list.

This section describes how to use these user applications. For information on installing and configuring Recording Controls refer to the *API Programmer Guide*. For additional information on logs and debugging, see the *Troubleshooting Guide*.

Recording Controls IP Phone Service

The Recording Controls IP Phone Service is an IP phone service application available on a hard or soft IP phone. Agents or knowledge workers who are configured for Desktop Recording, Network Recording, or Server Recording (SPAN) on their supported hard or soft IP phone can use the Recording Controls IP Phone Service.

Accessing the Recording Controls IP Phone Service

To access the IP Phone Service:

1. From your Cisco IP phone or Cisco IP Communicator soft phone, press the Services button.

The Services menu appears.



2. Select the IP phone service for the Recording Controls.

In this example, the name of Recording Controls IP Phone Service application is Recording Control.


The Recording Controls base screen appears.



3. Press the button for the command you want to use.

To see additional commands, press the More button.


The base screen displays additional recording control commands.



Recording Controls Commands for the IP Phone Service

The Recording Controls base screen is the launching pad for recording control commands. The recording control commands appear at the bottom of the screen. To see additional commands, press the More button.

The Recording Controls commands are simple one-button commands. When you press a command button, it sends the command to the configured Network Recording service for processing. Because the Network Recording service does not reply to these commands with success or failure messages, the Recording Controls application cannot report this information to you. The Recording Controls application can only report whether the command was sent successfully or not. This information appears on the Command results screen.



The previous figure indicates that the Recording Controls successfully sent the pause command. If Recording Controls could not send the command, an error message appears. If Recording Controls could not send the command, try sending the command again. If the command fails again, there might be a networking or configuration issue that is preventing the Recording Controls application from sending the command. You must correct the problem to resolve the issue before the Recording Controls application can work properly.

The Metadata button initiates the Add Metadata command. This differs from the other recording control commands because it requires additional information. You must select the defined metadata field you want to attach to the call recording, and then assign a value to the field.


When you press the Metadata button, the Metadata menu screen appears.



The metadata fields that appear in the menu are defined in Monitoring and Recording Administrator.

Use the Up and Down buttons to scroll up and down the list to see all defined metadata fields. Select a metadata item and highlight it, and then press the Select button, or press the number button on the IP phone keypad that matches the menu item number shown on the screen.

When you have selected a metadata item, the Recording Controls IP Phone Service Metadata value screen appears. This screen displays the name of the selected metadata item and provides an interface for you to input a value for the selected item.



Use the IP phone keypad to enter numbers and letters in the Value field. Then press Submit.



Each metadata value is associated with a metadata type. The metadata type determines the type of characters you can enter in the metadata field. The valid metadata types are text, date, and number.

If the metadata field is assigned the text metadata type, you can enter alphanumeric characters from the keypad. To choose a letter or number, press the key associated with the character repeatedly until the character appears on the screen.

Example 1: Key 2 allows you to choose from the following characters: a b c 2 A B C. To select A, press key 2 five times. Repeat for each character you want to include in the metadata field.

If the metadata field is assigned the date or number metadata type, you can enter numbers from the keypad.

Example 2: Press key 1 to enter 1 in the metadata field. The * and # keys provide additional symbols, including the dash/minus symbol and the decimal point.

Note: The metadata field does not allow the following characters: & < >

Example 3: The user typed Gold in the value field for metafield1 and pressed Submit to send the command. The Metadata Results screen appears with a message.



The Metadata Results screen indicates whether the sent metadata command succeeded or failed. The message includes the name of the metadata field and the value entered for the metadata command.

While you accept and make phone calls using a hard or soft IP phone, the Recording Controls IP Phone Service screen might be replaced with other screens from the system or other services. In these cases, you can simply press the Services button again and select the Recording Controls IP Phone Service to continue sending recording commands.


Press the Exit button to return to the Recording Controls IP Phone Service base screen.

Press the Services button to exit the Recording Controls IP Phone Service and return to the phone's base screen. Press the More button to return to the Recording Controls base screen.












Note: Some hard IP phones might display the Cancel button instead of the Exit button. The screen examples in this document use the Cisco IP Communicator soft phone.

Recording Controls Browser Application

Recording Controls is a web-based application. It is the launching pad for recording control commands.



The following table lists the command buttons that can appear in the Recording Controls window.

Icon	Label
	Record Tag
	Pause
	Resume
	Delete
	Login
	Logout
	Metadata The Metadata Key and Metadata Value fields are associated with this button.
	Start Segment
	Stop Segment
	Start Screen
	Stop Screen

Note: The Start Screen and Stop Screen commands are not displayed by default. They must be configured to appear by your administrator.

To access Recording Controls:

1. Enter the following URL in Internet Explorer:

`http://<base server>/recordingcontrols`

Where <base server> is the host name or IP address of the server that hosts Unified Workforce Optimization.

2. Depending on how your system is configured, you might be prompted to enter your username. This is the same username you use to log in to Unified Workforce Optimization. If

there is more than one domain, select your domain from the Choose Domain drop-down field.

To send metadata commands:

1. From the Recording Controls window, choose a metadata key from the Metadata Key drop-down list.
2. Enter a value in the Metadata Value field or leave it blank and then click the Metadata button.
 - If the metadata type is text, enter one or more alphanumeric characters.
 - If the metadata type is date or number, enter an integral number or calendar date. Valid characters when entering numbers are 0–9, a minus sign, and a decimal point.

Note: The Metadata Value field does not allow the following characters: & < >

Recording Controls sends the metadata command.

Note: Metadata sent after the call is completed might take up to an hour or more to display in the database.

Recording Commands

Recording commands allow you to control recordings.

Command Functions

The following sections describe how the recording commands interact with each other and the Quality Management components.

Record Command

The Record command records a call and uploads the call to the Quality Management server at the end of the day.

In the Recording Controls API, the <command> is record.

The Record command behaves as follows:

- Agent Recording—marks a call for recording, even if archiving is not enabled and the call does not meet the workflow criteria. The Record command overrides both the Don't

Record list and the workflow classifiers.

- Gateway/MediaSense Recording—marks a recording as tagged if archiving is enabled and the call meets the workflow criteria. The Record command overrides the workflow, but does not override an exclusion list in the Exclusion List window because the root contact does not know the agent's identity when recording. See “Recording Controls Considerations for Gateway Recording” in the *Administrator Guide* for more information.

Unified Workforce Optimization stores agent-tagged calls with the Agent Tagged reason code and saves them for the retention time configured in Unified Workforce Optimization.

Agent Recording:

- The Record command is valid for the active call and the last call.
- If Quality Management is not recording the active call, Quality Management starts recording the call when you invoke the command and adds the Agent Tagged reason code.
- If Quality Management is recording two active calls (for example, an inbound ACD call and an outbound consultation call), it tags the call that triggered the recording to begin.
- If Quality Management is not recording two active calls (for example, an inbound ACD call and an outbound consultation call), it begins recording the first call sent to the agent based on the call start times, and tags the first call when you invoke the Record command.

Gateway/MediaSense Recording and Agent Recording:

- When Quality Management actively recording a call, the Tag command adds the Agent Tagged reason code to the data associated with the call.
- When Quality Management is not actively recording a call, the Tag command changes the reason code associated with the last recorded call to the Agent Tagged reason.
- If Quality Management did not record the last call, nothing happens. Quality Management cannot update the reason code when no recording is available.

Pause Command

The Pause command temporarily halts the recording of:

- Audio—the audio recording is silent for the duration of the pause in the final recording.
- Screen—the screen recording displays pause symbol for the duration of the pause in the final recording.

When you play back a recording that contains an event with a QM Pause macro, the audio portion is silent and the screen portion displays the pause symbol.

Use the Pause command when you cannot record sensitive information (such as credit card numbers) for security or liability reasons. The Pause command allows you to omit sensitive information from the final recording. This command adheres to the Payment Card Industry Data Security Standard (PCI DSS) for protecting consumer data.

Calls are available for playback prior to reconciliation with silence where an agent used the Pause command. These calls are accessible by anyone with the archive user role.

Agent Recording:

- The pause command is valid for active calls only.
- If you send a pause command for a call currently in the paused state, the pause command has no effect.
- The pause command does not affect live monitoring.

Gateway/MediaSense Recording delays the pause. The pause will appear in the recording after the recording is uploaded.

Issue the Resume command when you want to start recording after a pause.

Resume Command

The Resume command resumes recording after you issued a Pause command to stop the recording.

In the Recording Controls API, the <command> is resume.

Agent Recording:

- The Resume command affects voice and screen recording.
- If the call is not currently paused, the Resume command has no effect.
- The Resume command is valid for active calls only.
- If you do not use the Resume command, the point at which you paused the recording is the end of the audio recording.
- A Resume command does not appear as a mutual silence event or talkover event during post-call processing.

Delete Command

The Delete command marks a recording for deletion, even if archiving is enabled, the call meets workflow criteria, the extension is in the inclusion list, or it is tagged for retention. The Delete command deletes the recorded files and any metadata, and uploads the basic contact data to Quality Management to maintain accurate call counts.

- The Delete command is valid for the active call only.
- The Delete command has precedence over all other commands.
- Once you delete a call you cannot record it by issuing the Record command.

- Deleted calls are not available for archive purposes or quality management purposes.
- You cannot view deleted calls in Unified Workforce Optimization.
- For Gateway/MediaSense Recording, the recording is deleted for the person who sends the command, but the audio recording might continue to exist in the root call or in other calls associated with this call.

Login Command

The Login command sends a login request that associates an agent with the specific extension for hot desking. The Recording Controls IP phone service does not have login/logout capabilities. Use Cisco's Extension Mobility IP Phone application to log in by phone. This command is not supported if you are using Gateway/MediaSense Recording.

Logout Command

The Logout command sends a logout request that associates an agent with the specific extension for hot desking. This command is not supported if you are using Gateway/MediaSense Recording.

Metadata Command

The Metadata command attaches metadata to an active call. If Quality Management does not upload the current call (or previous) for archiving because of workflow criteria, then the metadata will be uploaded to the database but will not appear in the interface.

In the Recording Controls API, the <command> is metadata. You must include at least one key/value pair (<key>=<value> or <key>:<value>).

- The Metadata command is valid for the active call and the last call.
- You can associate maximum of 30 metadata items with a call. You can accomplish this with 30 Metadata commands containing one key/value pair each, or one Metadata command containing up to 30 key/value pairs.
- You can only attach metadata defined in Monitoring and Recording Administrator (Recordings > Metadata) to a call. If you add an unknown key to a Metadata command, Quality Management ignores the unknown key.

The Metadata command interacts with the active call, including the time up until the next call starts. If you invoke the Metadata command during a call, Quality Management uploads the metadata to the database at the same time as the rest of the call data. If you invoke the Metadata command after the call but before the next call, Quality Management uploads the metadata separately at the time you invoke the command and Quality Management stores the metadata with the last known call. Calls that occur after a recorded call that do not match the inclusion list are not counted as the next call.

Note: Quality Management resets the last known call at login, so Quality Management cannot attach metadata to the last known call before logout or shutdown after the next login occurs.

Quality Management attaches metadata to calls that span the configured end of day/upload time.

Successive calls to the Metadata command using the same key name update the existing metadata for that call.

Specifying an empty value for a key removes that metadata field association for the call.

Valid formats for metadata are as follows.

- Dates—Dates must be in yyyy-mm-dd format.
- Numbers—Numbers can start with and contain a decimal point (for example, valid numbers are .30, 10.7, and 2500). Numbers cannot end with a decimal point or contain a comma (for example, invalid numbers are 30. and 2,500).
- Text—Text key values cannot contain these reserved characters: & =

All other alphanumeric characters are valid. You can find the decimal point in the * key menu and the dash in the zero key menu on your phone.

Start Segment Command

The Start Segment command starts the audio and screen recording of an active call. This command allows you to override the automatic exclusion lists to start recording their current call and treat it as a normal contact.

In the Recording Controls API, the <command> is start.

Agent Recording:

- If Quality Management is not currently recording an active call, the Start Segment command starts audio and screen recording.
- If Quality Management is currently recording an active call, the Start Segment command has no effect.
- If the active call ends before the recording is stopped by the agent, the recording is saved according to workflow criteria.
- The Start Segment command does not override the workflow.
- The Start Segment command does override the exclusion list in the Exclusion List window because the root call does not know the agent's identity when recording.

Example: If you are using an Outbound Dialer, you can add the Outbound Dialer to the exclusion list to prevent recording from starting when an agent logs in. The

agent can use the Start Segment and Stop Segment commands to override the exclusion list and record each outbound call. For more information, refer to [Using Commands with an Outbound Dialer](#).

Gateway/MediaSense Recording does not support the Start Segment command.

Stop Segment Command

The Stop Segment command stops the audio and screen recording of an active call. The recording is then saved according to workflow criteria as a new contact.

In the Recording Controls API, the <command> is stop.

Desktop Recording supports the Stop Segment command only during active calls.

- Agent Recording supports the Stop Segment command only during active calls.
- Gateway/MediaSense Recording does not support the Stop Segment command.

The agent can use the Stop Segment command to stop the recording after a sale has been made and before payment information is taken in order to omit customer data in adherence with PCI DSS.

Start Screen Command

The Start Screen command starts screen recording regardless of whether or not you are participating in an active call. Use this command to record chat or email interactions with a customer.

Voice contact recordings and screen-only contact recordings can be bracketed or interleaved.

Example: You can send the Start Screen command to record your screen while not participating in an active call. If you receive a phone call or make a call during this time, a separate voice and screen contact might be created according to workflow (or you can send the Start Segment and Stop Segment commands to create the contact). After the active call has ended, another screen only contact is created and will continue until you send the Stop Screen command.

Agent Recording:

- If Quality Management is not currently recording an active call, the Start Screen command starts screen only recording.
- If Quality Management is currently recording an active call, the Start Screen command has no effect on the current recording. The screen only recording will begin after the active call has ended (if the Stop Screen command has not been issued). The call recording and the screen only recording are saved as separate contact recordings.

Gateway/MediaSense Recording does not support the Start Screen command.

After issuing the Start Screen command, you can send other commands. The following list contains the commands that are supported with screen-only recording and the expected behavior.

- **Pause**—Pauses the current screen-only recording
- **Resume**—When sent after the Pause command, resumes the screen-only recording
- **Restart**—Stops the screen-only recording, deletes that recording, and restarts the screen-only recording from the point when you issued the Restart command.

Note: The Restart command is not supported with Gateway Recording and will be removed in a future release.

- **Delete**—Deletes the screen-only recording. You must send the Stop Screen command either before or after the Delete command in order to be able to send the Start Screen command again to start another screen-only recording.
- **Metadata**—Attaches metadata to the active screen only recording

All other commands have no affect on the current screen-only recording.

Issue the Stop Screen command to stop screen-only recording.

Stop Screen Command

The Stop Screen command stops screen recording.

In the Recording Controls API, the <command> is stop_screen. You must include at least one key/value pair.

Example: <key>=<value> or <key>:<value>

Agent Recording:

- If Quality Management is currently recording screen-only, the Stop Screen command stops the screen recording. The Stop Screen command only has an effect if you previously issued the Start Screen command.
- If the Stop Screen command is not sent after the Start Screen command, the maximum contact recording length is 4 hours.

Gateway/MediaSense Recording does not support the Stop Screen command.

Config Command

The Config command displays configuration information for the specified user. A user is configured for desktop recording if no serverHost is returned. In this case you need to send commands via the applet, not the server.

Effect of Issuing Recording Control Commands

The following table describes the effect of issuing a recording command when the call is currently being recorded and when the call is not being recorded.

Command	Currently Recording	Not Currently Recording
Record	Sets Reason Code to TAGGED.	Call recording starts. Sets Reason Code to TAGGED.
Pause	Recording paused.	None.
Pause URL	Recording paused.	None.
Resume	Recording resumes (if previously paused).	None.
Restart	Recording restarts. Sets Reason Code to TAGGED.	Recording starts. Sets Reason Code to TAGGED.
Delete	Call deleted.	None.
Start Segment	None.	Recording starts.
Stop Segment	Recording stops and is saved according to workflow criteria.	None.
Start Screen	If there is a current voice and screen recording, the Start Screen command has no effect on the current recording. The screen-only recording will begin after the active call has ended (if the Stop Screen command has not been issued) and will be created as a separate contact recording. If there is a current screen-only recording, the Start Screen command has no effect.	Screen only recording starts.
Stop Screen	If there is a current screen-only recording, screen recording stops. The Stop Screen command has an effect only if you previously issued the Start Screen command.	None.

Active and Last Call

It is important to understand the difference between the terms *active call* and *last call*. Some commands can apply to either one of these call types. Some commands can apply to a single call type.

- An **active call** occurs when the Unified Workforce Optimization user is on a call with one or more parties. A call on hold is still an active call. The active call starts when the user receives the call (phone is ringing) or makes a new call. The active call ends when the user hangs up the phone.
- The **last call** is the previously recorded call. Any valid recording commands sent after a call ends, and until another call that matches the inclusion list is received or made by the user, apply to the last call.

Command	Applies to Active Call	Applies to Last Call
Pause	Yes	No
Pause URL	Yes	No
Resume	Yes	No
Record	Yes	No
Restart	Yes	No
Delete	Yes	No
Login	No—The recording command applies to the next active call.	No
Logout	Yes—An active call stop recording.	No
Metadata	Yes	Yes
Segment and Save	Yes	No
Segment and Delete	Yes	No
Start Screen	Yes—And when there is no active call.	No
Stop Screen	Yes—And when there is no active call.	No

Using Commands with an Outbound Dialer

An outbound dialer creates a single “nailed up” call for the entire time you are logged in. This results in all of your outbound calls being combined into one large recording, even though you might make numerous outbound calls during your session. Use the Start Segment and Stop Segment commands to break this large nailed up call into multiple contact recordings.

Send the Start Segment command at the beginning and the Stop Segment command at the end of each outbound call to create a unique contact recording for each outbound call. The Start Segment command starts the audio and screen recording of an active call. The Stop Segment command stops the recording. The recording is then saved according to workflow criteria as a new contact. Send the Start Segment command again at the beginning of your next outbound call to start another unique contact recording.